
ROT2PROG Protocol Documentation

Table of contents

- ROTh_CMD_CALIBRATION
- ROTh_CMD_CFG_GET
- ROTh_CMD_CFG_SET
- ROTh_CMD_CLEAN
- ROTh_CMD_GET_ANGLES
- ROTh_CMD_GET_ANGLES_100
- ROTh_CMD_GET_MEM
- ROTh_CMD_GET_OUTS
- ROTh_CMD_GET_SOFT_HARD
- ROTh_CMD_MOTORS
- ROTh_CMD_POWER
- ROTh_CMD_RESTART_DEVICE
- ROTh_CMD_SET_ANGLES
- ROTh_CMD_SET_ANGLESX
- ROTh_CMD_SET_ANGLES_100
- ROTh_CMD_SET_MEM_FINISH
- ROTh_CMD_SET_MEM_INIT
- ROTh_CMD_SET_MEM_PACKET
- ROTh_CMD_SET_OUTS
- ROTh_CMD_SET_SOFT_HARD
- ROTh_CMD_STOP

ROTx_CMD_CALIBRATION

Description

Set rotor position(s) without moving

```
angleToSend = IntToString(360 * divisor + (desiredAngle * di
```

Command value:

0xf9

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes												
0x00	0x01 0x02 0x03 0x04 0x05					0x06 0x07 0x08 0x09 0x0a					0x0b	0x0c
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadRot2actMotor										command: prtROTxCommand	magicEnd: prtROTxMagicNumber
uint8 t	angle1: char[4]				angle1Divisor: uint8 t	angle2: char[4]				angle2Divisor: uint8 t	uint8 t	
Example												
0x57	0x33	0x36	0x31	0x30	0x0a	0x33	0x35	0x39	0x30	0x0a	0x39	0x20
'W'	'3'	'6'	'1'	'0'	'a	'3'	'5'	'9'	'0'	'a	'9'	' '
Set Motor 1 to 1 degree and Motor 2 to -1 degree												

Response data structure

Data structure name

prtROTxResponseAngle

Description

Get rotor position.

```
angle = StrToInt(receivedAngle) * divisor - 360 * divisor
```

Data structure details

Response Magic Number

```
rotxMagicStart 0x57
```

Response Magic Number End

```
rotxMagicEnd 0x20
```

Bytes											
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b
magic: prtROtsMagicNumber	angle1: array				angle1Divisor: c_ubyte		angle2: array		angle2Divisor: c_ubyte		magicEnd: prtROtsMagicNumber
prtROtsMagicNumber:uint8_t		char[4]			uint8_t		char[4]		uint8_t		prtROtsMagicNumber:uint8_t
Example											
0x57	0x33	0x38	0x32	0x33	0x0a	0x33	0x36	0x30	0x35	0x0a	0x20
'W'	'3'	'8'	'2'	'3'	'\a	'3'	'6'	'0'	'5'	'\a	' '
Motor 1 angle: 22.3 degree, Motor 2 angle: 0.5 degree											

Motor 1 angle: 22.3 degree, Motor 2 angle: 0.5 degree

ROTn_CMD_CFG_GET

Description

Get settings value. isSketchValue determines, if response provides value for current running settings or for prepared settings to be applied in bulk. Passing fieldId = 0 in response returns maximum fieldId in fieldValue.f_word

Command value:

0xcf

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes												
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	0x0c
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadRot2cmdGetValue										command: prtROTxCommand	magicEnd: prtROTxMagicNumber
uint8 t	fieldId: uint16 t	isSketchValue: uint8 t		0	0	0	0	0	0	0	uint8 t	uint8 t
Example												
0x57	0x02	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0xcf	0x20
W	x2	x0	x0	x0	x0	x0	x0	x0	x0	x0	xcf	r
Get value for fieldId = 2 (motor_0_min_angle) for running settings (isSketchValue=0)												

Response data structure

Data structure name

prtrOTxResponseGetValue

Description

Data structure details

Response Magic Number

```
rotxMagicStartResponseCfgGetValue 0x
```

[illegible]

Description

Set settings value. isSketchValue determines, if response provides value for current running settings or for prepared settings to be applied in bulk. applySketchValues = 1 will write all stored with isSketchValue = 1 settings to device settings.

0xf0

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes																
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b				0x0c	
magic: prtROTxxMagicNumber	payload: prtROTxxRequestPayloadRot2cmdSetValue												command: prtROTxxCommand		magicEnd: prtROTxxMagicNumber	
uint8 t	fieldId: uint16 t				isSketchValue: uint8 t				fieldValue: None				0		0	uint8 t
Example																
0x57	0x02	0x00	0x00	0x00	0x00	0x00	0x00	0xb4	0x43	0x00	0x00	0x0f			0x20	
'W'	x2	x0	x0	x0	x0	x0	x0	xb4	C	x0	x0	xf			'	
Set value of 360 (float) for field fieldId = 2 (motor_0_min_angle) for running settings (isSketchValue=0)																

Data structure name

prtROTxResponseGetValue

Description

Data structure details

Response Magic Number

rotxMagicStartResponseCfgGetValue 0x

[illegible]

ROT_n_CMD_CLEAN

Description

Set both motors position to 0, without moving.

Command value:

0xf8

Data structure

Data structure name

pvtROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes 0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	0x0c
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadIgnored										command: prtROTxCommand	magicEnd: prtROTxMagicNumber
uint8 t	ignored: uint8 t[10]										uint8 t	uint8 t
Example												
0x57	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x20
W'	x0	x0	x0	x0	x0	x0	x0	x0	x0	x0	x0	r
Move Motor 1 to 5.54 degree and Motor 2 to 10.05 degree												

Response data structure

Data structure name

prtrOTxResponseAngle

Description

Get rotor position.

```
angle = StrToInt(receivedAngle) * divisor - 360 * divisor
```

Data structure details

Response Magic Number

```
rotxMagicStart 0x57
```

Response Magic Number End

```
rotxMagicEnd 0x20
```

Bytes											
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b
magic: ptrROTxMagicNumber	angle1: array				angle1Divisor: c_ubyte	angle2: array		0x08	0x09	angle2Divisor: c_ubyte	magicEnd: ptrROTxMagicNumber
(ptrROTxMagicNumber:uint8_t)	char[4]				uint8_t	char[4]				uint8_t	(ptrROTxMagicNumber:uint8_t)
Example											
0x57	0x33	0x38	0x32	0x33	0x0a	0x33	0x36	0x30	0x35	0x0a	0x20
'W'	3	8	2	3	xa	3	6	0	5	xa	' '
Motor 1 angle: 22.3 degree, Motor 2 angle: 0.5 degree											

ROTN_CMD_GET_ANGLES

Description

Get current motors positions

Command value:

0x1f

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes																		
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b					0x0c		
magic: ptrROTxMagicNumber											payload: ptrROTxRequestPayloadIgnored				command: ptrROTxCommand		magicEnd: ptrROTxMagicNumber	
uint8 t											ignored: uint8_t[10]				uint8 t		uint8 t	
Example																		
0x57	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x1f					0x20		
'W'	x0	x0	x0	x0	x0	x0	x0	x0	x0	x0	x1f					.		

Response data structure

Data structure name

prtrOTxResponseAngle

Description

Get rotor position.

```
angle = StrToInt(receivedAngle) * divisor - 360 * divisor
```

Data structure details

Response Magic Number

```
rotxMagicStart 0x57
```

Response Magic Number End

```
rotxMagicEnd 0x20
```

Bytes 0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b
magic: ptrROTsmagicNumber	angle1: array				angle1Divisor: c_ubyte		angle2: array		angle2Divisor: c_ubyte		magicEnd: ptrROTsmagicNumber
(ptrROTsmagicNumber+uint8_t)	char[4]				uint8_t		char[4]		uint8_t		(ptrROTsmagicNumber+uint8_t)
Example											
0x57	0x33	0x38	0x32	0x33	0x0a	0x33	0x36	0x30	0x35	0x0a	0x20
'W'	'3'	'8'	'2'	'3'	'a'	'3'	'6'	'0'	'5'	'a'	' '
Motor 1 angle: 22.3 degree, Motor 2 angle: 0.5 degree											

Description

Get current motors positions. 0.01 resolution

Get current motors positions. 0.01 resolution

0x6f

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStartResponseAngle100 0x58
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

[illegible]

Data structure name

prtrOTxResponseAngle100

Get rotor position.

Get rotor position.

```
angle = StrToInt(receivedAngle) * 100 - 360 * 100
```

Data structure details

Response Magic Number

```
rotxMagicStartResponseAngle100 0x58
```

Response Magic Number End

```
rotxMagicEnd 0x20
```

Bytes												
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	
magic: prtROTxMagicNumber	angle1: array					angle2: array					magicEnd: prtROTxMagicNumber	
prtROTxMagicNumber:uint8_t	char[5]					char[5]					prtROTxMagicNumber:uint8_t	
Example												
0x58	0x33	0x38	0x32	0x33	0x33	0x33	0x36	0x30	0x35	0x32	0x20	
'X'	3'	8'	2'	3'	3'	3'	6'	0'	5'	2'	1'	
Motor 1 angle: 22.33 degree, Motor 2 angle: 0.52 degree												

ROTn_CMD_GET_MEM

Description

Get configuration memory data

Command value:

0x4f

Data structure

Data structure name

prtROTxRequest

Data structure details

Request Magic Number

rotxMagicStart 0x57

Request Magic Number End

rotxMagicEnd 0x20

Bytes												
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	0x0c
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadRot2getMem										command: prtROTxCommand	magicEnd: prtROTxMagicNumber
uint8 t	bugId: uint8 t	0	0	0	0	0	0	0	0	0	uint8 t	uint8 t
Example												
0x57	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x4f	0x20
W	x0	x0	x0	x0	x0	x0	x0	x0	x0	x0	O	.

Response data structure

ROTN_CMD_GET_OUTS

Description

Get SW01 outputs state

Command value:

0x3f

Data structure

Data structure name

prrOTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

[illegible]

Response data structure

Data structure name

prrROTxResponseGetOuts

Description

SW01 outputs

Data structure details

Response Magic Number

```
rotxMagicStartResponseGetOuts 0x3f
```

Bytes	Bytes
0x00	0x01
magic: ptrROTxMagicNumber	pins: c ubyte
(ptrROTxMagicNumber/uint8_t)	uint8_t
Example	
0x3f	0x23
x3f	x23
Outputs state: 100011	

ROtn_CMD_GET_SOFT_HARD

Description

Get START and STOP settings (IMMEDIATELY/SOFTLY)

Command value:

Oxal

Data structure

Data structure name

pvtROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

[illegible]

Response data structure

Data structure name

prtrOTxResponseGetSoftHard

Description

Start and Stop settings

Data structure details

Response Magic Number

```
rotxMagicStart 0x57
```

Response Magic Number End

```
rotxMagicEnd 0x20
```

Bytes																	
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b						
magic: ptrROTxMagicNumber	unused: array				manualCtlStart: scMotorSoftStart				unused2: array				manualCtlStop: scMotorSoftStart				magicEnd: ptrROTxMagicNumber
(ptrROTxMagicNumber:uint8_t)	uint8_t[4]				scMotorSoftStart:uint8_t)				uint8_t[4]				scMotorSoftStart:uint8_t)				(ptrROTxMagicNumber:uint8_t)
Example																	
0x57	0x00	0x00	0x00	0x00	0x00		0x00	0x00	0x00	0x00	0x00				0x20		
'W'	x0	x0	x0	x0	x0		x0	x0	x0	x0	x0				'		

START and STOP set to SOFTLY

seMotorSoftStart values:

- sstHard = 0
- sstSoft = 1

ROTx_CMD_MOTORS

Description

Command motors move (left/right etc.)

Command value:

0x14

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes													
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	0x0c	
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadRot2cmdMotors										command: prtROTxCommand	magicEnd: prtROTxMagicNumber	
uint8 t	command: (prtROTxMoveMotorsCmd:uint8 t)	0	0	0	0	0	0	0	0	0	uint8 t	uint8 t	
Example													
0x57	0x05	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x14	0x20	
W	x5	x0	x0	x0	x0	x0	x0	x0	x0	x0	x14	''	
Command Motor 1 to move Left, and Motor 2 to move Up prtROTxRequestPayloadRot2cmdMotors values:													
<ul style="list-style-type: none">• mmsCmdStop = 0x00• mmsCmdLeft = 0x01• mmsCmdRight = 0x02• mmsCmdUp = 0x04• mmsCmdDown = 0x08• mmsCmdLeftUp = 0x05• mmsCmdRightUp = 0x06• mmsCmdLeftDown = 0x09• mmsCmdRightDown = 0x0A													

ROTx_CMD_POWER

Description

Set motors power (0-100%). (Applied immediately, without stoping current move)

Command value:

0xf7

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes												
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	0x0c
magic: prtROTxMagicNumber		payload: prtROTxRequestPayloadRot2power								command: prtROTxCommand		magicEnd: prtROTxMagicNumber
uint8 t		unused: uint8 t[4]		max_power_motor1: uint8 t		unused2: uint8 t[4]				max_power_motor2: uint8 t		uint8 t
Example												
0x57	0x00	0x00	0x00	0x00	0x4d	0x00	0x00	0x00	0x00	0x42	0x17	0x20
W'	x0	x0	x0	x0	M'	x0	x0	x0	x0	B'	x7	"

Set MAXIMUM POWER on Motor 1 to 77% and Motor 2 to 66%

Response data structure

Data structure name

prtrOTxResponseAngle

Description

Get rotor position.

```
angle = StrToInt(receivedAngle) * divisor - 360 * divisor
```

Data structure details

Response Magic Number

```
rotxMagicStart 0x57
```

Response Magic Number End

```
rotxMagicEnd 0x20
```

Bytes											
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b
magic: ptrROTxMagicNumber	angle1: array				angle1Divisor: c_ubyte	angle2: array		0x08	0x09	angle2Divisor: c_ubyte	magicEnd: ptrROTxMagicNumber
(ptrROTxMagicNumber:uint8_t)	char[4]				uint8_t	char[4]				uint8_t	(ptrROTxMagicNumber:uint8_t)
Example											
0x57	0x33	0x38	0x32	0x33	0x0a	0x33	0x36	0x30	0x35	0x0a	0x20
'W'	3	8	2	3	xa	3	6	0	5	xa	' '
Motor 1 angle: 22.3 degree, Motor 2 angle: 0.5 degree											

ROTn_CMD_RESTART_DEVICE

Description

Restarts device after 5 seconds. Payload restartConfirmValue must be set to: rotxMagicRestartDevice

Command value:

0xee

Data structure

Data structure name

prtROTxRequest

Data structure details

Request Magic Number

rotxMagicStart 0x57

Request Magic Number End

rotxMagicEnd 0x20

Bytes												
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	0x0c
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadRot2cmdRestart									command: prtROTxCommand	magicEnd: prtROTxMagicNumber	
uint8 t	restartConfirmValue: (prtROTxRestartMagicNumber/None)				0	0	0	0	0	0	uint8 t	uint8 t
Example												
0x57	0xef	0xbe	0xad	0xde	0x00	0x00	0x00	0x00	0x00	0x00	0xee	0x20
W	xf	be	ad	de	x0	x0	x0	x0	x0	x0	ee	'
Restarts device after 5 seconds delay.												

Response data structure

Data structure name

prtROTxResponseRestartDevice

Description

Data structure details

Response Magic Number

rotxMagicStart 0x57

Response Magic Number End

rotxMagicEnd 0x20

Bytes											
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b
magic: prtROTxMagicNumber	status: c_ubyte	unused: array								magicEnd: prtROTxMagicNumber	
(prtROTxMagicNumber/uint8_t)	uint8_t	uint8_t[9]								(prtROTxMagicNumber/uint8_t)	

ROT_n_CMD_SET_ANGLES

Description

Move motors to position.

```
angleToSend = IntToString(360 * divisor + (desiredAngle * divisor
```

Command value:

0x2f

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes														
0x00	0x01		0x02	0x03	0x04	0x05	0x06		0x07	0x08	0x09	0x0a	0x0b	0x0c
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadRot2accMotor												command: prtROTxCommand	magicEnd: prtROTxMagicNumber
uint8 t	angle1: char[4]				angle1Divisor: uint8 t		angle2: char[4]				angle2Divisor: uint8 t		uint8 t	uint8 t
Example														
0x57	0x33	0x36	0x35	0x35	0x0a			0x33	0x37	0x30	0x30	0x0a	0x2f	0x20
'W'	'3'	'6'	'5'	'5'	'a			'3'	'7'	'0'	'0'	'a	'f'	' '
Move Motor 1 to 5.5 degree and Motor 2 to 10 degree														

Response data structure

Data structure name

prtROTxResponseAngle

Description

Get rotor position.

```
angle = StrToInt(receivedAngle) * divisor - 360 * divisor
```

Data structure details

Response Magic Number

```
rotxMagicStart 0x57
```

Response Magic Number End

```
rotxMagicEnd 0x20
```

Bytes 0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b
magic: prtROtsMagicNumber	angle1: array				angle1Divisor: c_ubyte		angle2: array		angle2Divisor: c_ubyte		magicEnd: prtROtsMagicNumber
prtROtsMagicNumber:uint8_t	char[4]				uint8_t		char[4]		uint8_t		prtROtsMagicNumber:uint8_t
Example											
0x57	0x33	0x38	0x32	0x33	0x0a	0x33	0x36	0x30	0x35	0x0a	0x20
'W'	'3'	'8'	'2'	'3'	'a'	'3'	'6'	'0'	'5'	'a'	' '
Motor 1 angle: 22.3 degree, Motor 2 angle: 0.5 degree											

Motor 1 angle: 22.3 degree, Motor 2 angle: 0.5 degree

ROTn_CMD_SET_ANGLESX

Description

Move motors to position.

```
angleToSend = IntToString(360 * divisor + (desiredAngle * divisor)
```

Command value:

0xf2

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes														
0x00	0x01		0x02	0x03	0x04	0x05	0x06		0x07	0x08	0x09	0x0a	0x0b	0x0c
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadRot2setMotor										command: prtROTxCommand		magicEnd: prtROTxMagicNumber	
uint8 t	angle1: char[4]			angle1Divisor: uint8 t			angle2: char[4]			angle2Divisor: uint8 t			uint8 t	uint8 t
Example														
0x57	0x33	0x36	0x35	0x35	0x0a		0x33	0x37	0x30	0x30	0x0a		0x12	0x20
W'	3'	6'	5'	5'	xa		3'	7'	0'	0'	xa		x12	'
Move Motor 1 to 5.5 degree and Motor 2 to 10 degree														

Response data structure

Data structure name

prtROTxResponseAngle

Description

Get rotor position.

```
angle = StrToInt(receivedAngle) * divisor - 360 * divisor
```

Data structure details

Response Magic Number

```
rotxMagicStart 0x57
```

Response Magic Number End

```
rotxMagicEnd 0x20
```

Bytes											
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b
magic: prtROTsmagicNumber	angle1: array				angle1Divisor: c_ubyte		angle2: array		angle2Divisor: c_ubyte		magicEnd: prtROTsmagicNumber
(prtROTsmagicNumber/uint8_t)	char[4]				uint8_t	char[4]		uint8_t		(prtROTsmagicNumber/uint8_t)	
Example											
0x57	0x33	0x38	0x32	0x33	0x0a	0x33	0x36	0x30	0x35	0x0a	0x20
'W'	3	8	2	3	xa	3'	6'	0'	5'	xa	'
Motor 1 angle: 22.3 degree, Motor 2 angle: 0.5 degree											

ROTN_CMD_SET_ANGLES_100

Description

Move motors to position. This command allows to specify target position to 0.01 resolution.

```
angleToSend = IntToString(360 * 100 + (desiredAngle * 100))
```

Command value:

0x5f

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStartResponseAngle100 0x58
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes													
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	0x0c	
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadRot2startMotor100										command: prtROTxCommand		magicEnd: prtROTxMagicNumber
uint8 t	angle1: char[5]					angle2: char[5]					uint8 t	uint8 t	
Example													
0x57	0xc3	0xc6	0xc5	0xc5	0xc4	0xc3	0xc7	0xc0	0xc0	0xc5	0xc5f	0x20	
W*	3	6	5	5	4	3	7	0	0	5	f	0	
Move Motor 1 to 5.54 degree and Motor 2 to 10.05 degree													

Response data structure

Data structure name

prtrOTxResponseAngle100

Description

Get rotor position.

```
angle = StrToInt(receivedAngle) * 100 - 360 * 100
```

Data structure details

Response Magic Number

```
rotxMagicStartResponseAngle100 0x58
```

Response Magic Number End

```
rotxMagicEnd 0x20
```

Bytes											
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b
magic: prtROTxMagicNumber						angle1: array				angle2: array	
(prtROTxMagicNumber:uint8_t)						char[5]				char[5]	
magicEnd: prtROTxMagicNumber						(prtROTxMagicNumber:uint8_t)					
Example											
0x58	0x33	0x38	0x32	0x33	0x33	0x36	0x30	0x35	0x32	0x20	
X'	3'	8'	2'	3'	3'	6'	0'	5'	2'	'	
Motor 1 angle: 22.33 degree, Motor 2 angle: 0.52 degree											

ROTn_CMD_SET_MEM_FINISH

Description

Finish receiving configuration memory and save settings.

Command value:

0xf6

Data structure

Data structure name

prtROTxRequest

Data structure details

Request Magic Number

rotxMagicStart 0x57

Request Magic Number End

rotxMagicEnd 0x20

Bytes													
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	0x0c	
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadIgnored										command: prtROTxCommand	magicEnd: prtROTxMagicNumber	
uint8 t	ignored: uint8 t[10]										uint8 t	uint8 t	
Example													
0x57	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0xf6	0x20	
W	x0	x0	x0	x0	x0	x0	x0	x0	x0	x0	xf6	.	

Response data structure

Data structure name

prtROTxResponseSetMemFinish

Description

Data structure details

Response Magic Number

rotxMagicStart 0x57

Response Magic Number End

rotxMagicEnd 0x20

Bytes												
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	
magic: prtROTxMagicNumber	status: c ubyte		unused: array								magicEnd: prtROTxMagicNumber	
(prtROTxMagicNumber/uint8 t)	uint8 t		uint8 t[9]								(prtROTxMagicNumber/uint8 t)	

ROTn_CMD_SET_MEM_INIT

Description

Initialize receiving configuration memory data. Bank must be equal 1.

Command value:

0xf4

Data structure

Data structure name

prtROTxRequest

Data structure details

Request Magic Number

rotxMagicStart 0x57

Request Magic Number End

rotxMagicEnd 0x20

Bytes												
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	0x0c
magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadRot2InitReceiveParams										command: prtROTxCommand	magicEnd: prtROTxMagicNumber
uint8 t	unused5: uint8 t		bank: char[4]		length: char[4]				0	uint8 t		uint8 t
Example												
0x57	0x00	0x31	0x00	0x00	0x00	0x31	0x30	0x32	0x00	0x00	0xf4	0x20
W	x0	1'	x0	x0	x0	1'	0'	2'	x0	x0	xf4	.'

Response data structure

Data structure name

prtROTxResponseSetMemInit

Description

Data structure details

Response Magic Number

rotxMagicStart 0x57

Response Magic Number End

rotxMagicEnd 0x20

Bytes												
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	
magic: prtROTxMagicNumber	unknown: c_ubyte		unused: array								magicEnd: prtROTxMagicNumber	
[prtROTxMagicNumber/uint8_t]	uint8_t		uint8_t[9]								[prtROTxMagicNumber/uint8_t]	

ROTn_CMD_SET_MEM_PACKET

Description

Receive configuration memory data

Command value:

0xf5

Data structure

Data structure name

prtROTxRxParams

Data structure details

Request Magic Number

rotxMagicStartReceiveParams 0xf5

Bytes		
0x00	0x01	0x02
magic: prtROTxMagicNumber	length: c ushort	
(prtROTxMagicNumber/uint8 t)	uint16 t	

Response data structure

Data structure name

prtROTxResponseParamsData

Description

Data structure details

Response Magic Number

rotxMagicStart 0x57

Response Magic Number End

rotxMagicEnd 0x20

Bytes											
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b
magic: prtROTxMagicNumber	status: c ubyte	unused: array								magicEnd: prtROTxMagicNumber	
(prtROTxMagicNumber/uint8 t)	uint8 t	uint8 t[9]								(prtROTxMagicNumber/uint8 t)	

ROTN_CMD_SET_OUTS

Description

Write SW01 outputs.

Command value:

0xf3

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes 0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b	0x0c
Magic: prtROTxMagicNumber	payload: prtROTxRequestPayloadRot2setOuts										command: prtROTxCommand	MagicEnd: prtROTxMagicNumber
uint8 t	uint8 t	0	0	0	0	0	0	0	0	0	uint8 t	uint8 t
Example												
0x57	0x29	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x00	0x13	0x20
W'	x.29	x.0	x.0	x.0	x.0	x.0	x.0	x.0	x.0	x.0	x.13	z

Set SW01 output to: 101001

ROTn_CMD_SET_SOFT_HARD

Description

Set start/stop immediately or softly settings.

Command value:

0xa2

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

Bytes	0x01 0x02 0x03 0x04 0x05					0x06 0x07 0x08 0x09 0xa					0xb	0xc
magic: priROTxMagicNumber	payload: priROTxRequestPayloadRot2setSoftStart										command: priROTxCommand	magicEnd: priROTxMagicNumber
uint8 t	uint3: uint8 [4]		manual ctrl start: (seMotorSoftStart/uint8 t)			uint3: uint8 [4]		manual ctrl stop: (seMotorSoftStart/uint8 t)			uint8 t	
Example												
0x57	0x00	0x00	0x00	0x00	0x01	0x00	0x00	0x00	0x00	0x01	0xa2	0x20
'W'	x0	x0	x0	x0	x1	x0	x0	x0	x0	x1	xa2	'.'

Set START and STOP to IMMEDIATELY

seMotorSoftStart values:

- sstHard = 0
- sstSoft = 1

ROTN_CMD_STOP

Description

Stop motors immediately.

Command value:

0x0f

Data structure

Data structure name

prrROTxRequest

Data structure details

Request Magic Number

```
rotxMagicStart 0x57
```

Request Magic Number End

```
rotxMagicEnd 0x20
```

[illegible]

Response data structure

Data structure name

prtROTxResponseAngle

Description

Get rotor position.

```
angle = StrToInt(receivedAngle) * divisor - 360 * divisor
```

Data structure details

Response Magic Number

```
rotxMagicStart 0x57
```

Response Magic Number End

```
rotxMagicEnd 0x20
```

Bytes											
0x00	0x01	0x02	0x03	0x04	0x05	0x06	0x07	0x08	0x09	0x0a	0x0b
magic: ptrROTsMagicNumber		angle1: array			angle1Divisor: c_ubyte		angle2: array		angle2Divisor: c_ubyte		magicEnd: ptrROTsMagicNumber
(ptrROTsMagicNumber+uint8_t)		char[4]			uint8_t		char[4]		uint8_t		(ptrROTsMagicNumber+uint8_t)
Example											
0x57	0x33	0x38	0x32	0x33	0x0a	0x33	0x36	0x30	0x35	0x0a	0x20
'W'	'3'	'8'	'2'	'3'	'a	'3'	'6'	'0'	'5'	'a	' '
Motor 1 angle: 22.3 degree, Motor 2 angle: 0.5 degree											